

[Remoto] Haciendo WOL



- [Wake on Lan \(TECNOZERO\)](#)
- [Comando Linux wakeonlan: enciende tus equipos de manera remota](#)
- [Wikipedia - Wake on LAN](#)
- [Wake on Lan - Encendido remoto](#)
- [Wake On LAN/WAN - Encender remotamente un ordenador](#)
- [WOL \(Wake On Lan\) Remoto](#)
- [Encendido remoto Wake On Lan](#)
- [Wake On Lan - Lo hice y lo entendí](#)

Haciendo WOL desde Linux

- **Orden por consola.** Una posible orden es wakeonlan y puede ser necesario instalarla previamente

```
# aptitude install wakeonlan
```

El uso de esta orden:

```
usuario@host:~$ wakeonlan
Usage
  wakeonlan [-h] [-v] [-i IP_address] [-p port] [-f file] [[hardware_address] ...]

Options
  -h
      this information
  -v
      displays the script version
  -i ip_address
      set the destination IP address
      default: 255.255.255.255 (the limited broadcast address)
  -p port
      set the destination port
      default: 9 (the discard port)
  -f file
      uses file as a source of hardware addresses

See also
  wakeonlan(1)
```

- **Ejemplo** para en una única orden encender varios equipos:

```
wakeonlan -f macs.txt
```

donde previamente hemos creado el fichero macs.txt con la lista de MACs de los ordenadores que queremos encender

[macs.txt](#)

```
04:92:26:c3:8a:f8
64:51:06:36:0e:35
64:51:26:60:0e:3e
04:92:f6:c1:f3:c0
64:51:06:5b:f0:eb
```

64:51:26:51:07:c3

Haciendo WOL desde Windows

Hay múltiples programas que permiten hacerlo. Uno de ellos es [MagiWOL](#), que existe tanto en versión instalable como portable.



MagiWOL

- [MagiWOL versión portable 3.42](#)
- [MagiWOL versión portable 3.62](#)

Haciendo WOL desde un NAS Synology



- [How To Wake up Windows Machine via WOL from Synology NAS \(or any Linux Server\)](#)

Edit task

General

Task Settings

Notification

☒ Send run details by email

Email:

☐ Send run details only when the script terminates abnormally

Run command

User-defined script

```
synonet --wake 50:E5:49:31:DF:59 eth0;  
#ether-wake -i eth0 50:E5:49:31:DF:59;  
#etherwake -b 192.168.1.66 50:E5:49:31:DF:59;
```

OK

Cancel

From:
<https://euloxio.myds.me/dokuwiki/> - **Euloxio wiki**

Permanent link:
https://euloxio.myds.me/dokuwiki/doku.php/doc:tec:net:remoto:wol_basico:inicio?rev=1745599319

Last update: **2025/04/25 18:41**

